

The **settobox** package

Heiko Oberdiek
<heiko.oberdiek at gmail.com>

2008/08/11 v1.4

Abstract

Commands are defined for getting box sizes similar to \LaTeX 's `\settowidth` commands.

Contents

1	Usage	1
1.1	Get box dimensions	1
1.2	Set box dimensions	2
1.3	Move box	2
1.4	Example	2
1.4.1	Short example	2
1.4.2	Test file that shows box manipulations	2
2	Implementation	4
3	Installation	6
3.1	Download	6
3.2	Bundle installation	6
3.3	Package installation	6
3.4	Refresh file name databases	7
3.5	Some details for the interested	7
4	Catalogue	7
5	History	8
	[2000/02/11 v1.0]	8
	[2000/09/07 v1.1]	8
	[2006/02/20 v1.2]	8
	[2007/04/11 v1.3]	8
	[2008/08/11 v1.4]	8
6	Index	8

1 Usage

1.1 Get box dimensions

<code>\settoboxwidth{<\LaTeX length>}{<\LaTeX box>}</code>
<code>\settoboxheight{<\LaTeX length>}{<\LaTeX box>}</code>
<code>\settoboxdepth{<\LaTeX length>}{<\LaTeX box>}</code>
<code>\settoboxtotalheight{<\LaTeX length>}{<\LaTeX box>}</code>

A $\langle \text{\LaTeX} \text{ box} \rangle$ is allocated by `\newsavebox`. It can be filled by `\sbox` or the environment `\lrbox`. The commands above extract then the desired lengths.

1.2 Set box dimensions

```
\setboxwidth{\<LATEX box>}{\<LATEX length expression>}
\setboxheight{\<LATEX box>}{\<LATEX length expression>}
\setboxdepth{\<LATEX box>}{\<LATEX length expression>}
```

These commands allow the manipulation of the box. Package `calc` is supported in the $\langle L^A T_E X \text{ length expression} \rangle$. Also the following lengths are available in this expression:

<code>\width</code>	width of the box
<code>\height</code>	height of the box
<code>\depth</code>	depth of the box
<code>\totalheight</code>	totalheight of the box

Note, the base point (point at the left margin of the baseline) always remain constant.

1.3 Move box

```
\setboxmoveleft{\<LATEX box>}{\<LATEX length expression>}
\setboxmoveright{\<LATEX box>}{\<LATEX length expression>}
\setboxlower{\<LATEX box>}{\<LATEX length expression>}
\setboxright{\<LATEX box>}{\<LATEX length expression>}
```

Note, the box is shifted relative to the base point. The base point is always inside the box, however the width and height of the box change along with the movement.

1.4 Example

1.4.1 Short example

```
\newsavebox{\mybox}
\newlength{\mylength}
\sbox{\mybox}{Hello World}
\settoboxwidth{\mylength}{\mybox}
```

1.4.2 Test file that shows box manipulations

```
1 \<example>
2 %<<END
3 \documentclass{article}
4
5 \usepackage{settoebox}
6 \usepackage{calc}
7
8 \newsavebox{\mybox}
9
10 \setlength{\fboxsep}{0pt}
11 \setlength{\parindent}{20pt}
12 \setlength{\parskip}{10pt}
13 \pagestyle{empty}
14
15 % \test{#1}
16 % The macro is called with commands in #1 that manipulates
17 % the box \mybox. These commands along with the result of
18 % the manipulation is shown. Thus the essence of the
19 % macro is:
20 %
21 % a) \sbox{\mybox}{The cracy fox.}
```

```

22 %   b) #1 % manipulates \mybox
23 %   c) Print #1 commands.
24 %   d) Print box with frame
25 %
26 % The implemenation looks more weird:
27 \makeatletter
28 \newcommand*{\test}[1]{%
29   \par
30   \begingroup
31     \raggedright
32     \edef\x{\detokenize{#1}}%
33     \let\do\@makeoother
34     \dospecials
35     \catcode`\~\active
36     \catcode`\ =10\relax
37     \def~{\}%
38     \noindent
39     \texttt{\scantokens\expandafter{\x}}%
40   \par
41 \endgroup
42 \begingroup
43   \let~\relax
44   \sbox{\mybox}{The cracy fox.}%
45   #1%
46   A---\fbox{\usebox{\mybox}}---B%
47 \endgroup
48 \par
49 }
50 \makeatother
51
52 \begin{document}
53
54 \test{\setboxwidth{\mybox}{1.25\width}}
55 \test{\setboxheight{\mybox}{0pt}}
56 \test{\setboxheight{\mybox}{2\height}}
57 \test{\setboxdepth{\mybox}{\height}}
58 \test{\setboxmoveleft{\mybox}{5pt}}
59 \test{%
60   \setboxmoveleft{\mybox}{5pt}~%
61   \setboxwidth{\mybox}{\width + 5pt}%
62 }
63 \test{\setboxmoveright{\mybox}{0.5\width}}
64 \test{\setboxlower{\mybox}{\height}}
65 \test{\setboxraise{\mybox}{\depth}}
66 \test{%
67   \setboxmoveright{\mybox}{5pt}~%
68   \setboxwidth{\mybox}{\width + 5pt}~%
69   \setboxheight{\mybox}{\height + 5pt}~%
70   \setboxdepth{\mybox}{\depth + 5pt}%
71 }
72
73 \end{document}
74 %END
75 </example>

```

The result:

`\setboxwidth {\mybox }{1.25\width }`

A—The cracy fox.—B

`\setboxheight {\mybox }{0pt}`

A—The cracy fox.—B

```
\setboxheight {\mybox }{2\height }
```

A—The cracy fox.—B

```
\setboxdepth {\mybox }{\height }
```

A—The cracy fox.—B

```
\setboxmoveleft {\mybox }{5pt}
```

A—The cracy fox.—B

```
\setboxmoveleft {\mybox }{5pt}
\setboxwidth {\mybox }{\width + 5pt}
```

A—The cracy fox.—B

```
\setboxmoveright {\mybox }{0.5\width }
```

A—The cracy fox.—B

```
\setboxlower {\mybox }{\height }
```

A—The cracy fox.—B

```
\setboxraise {\mybox }{\depth }
```

A—The cracy fox.—B

```
\setboxmoveright {\mybox }{5pt}
\setboxwidth {\mybox }{\width + 5pt}
\setboxheight {\mybox }{\height + 5pt}
\setboxdepth {\mybox }{\depth + 5pt}
```

A—The cracy fox.—B

2 Implementation

```
76 (*package)
Package identification.
77 \NeedsTeXFormat{LaTeX2e}
78 \ProvidesPackage{settobox}%
79 [2008/08/11 v1.4 Assign box dimensions to length registers (HO)]
80 \newcommand*{\settoboxwidth}[2]{\setlength{#1}{\wd#2}}
81 \newcommand*{\settoboxheight}[2]{\setlength{#1}{\ht#2}}
82 \newcommand*{\settoboxdepth}[2]{\setlength{#1}{\dp#2}}
83 \newcommand*{\settoboxtotalheight}[2]{%
84   \setlength{#1}{\ht#2}%
85   \addtolength{#1}{\dp#2}%
86 }

\setboxwidth
87 \newcommand*{\setboxwidth}[2]{%
88   \settobox@length\wd{#1}{#2}%
89 }

\setboxheight
```

```

90 \newcommand*\setboxheight[2]{%
91   \settobox@length\ht{#1}{#2}%
92 }

\setboxheight

93 \newcommand*\setboxdepth[2]{%
94   \settobox@length\dp{#1}{#2}%
95 }

\setboxmoveleft

96 \newcommand*\setboxmoveleft[2]{%
97   \settobox@horiz{-}{#1}{#2}%
98 }

\setboxmoveright

99 \newcommand*\setboxmoveright[2]{%
100   \settobox@horiz{}{#1}{#2}%
101 }

\setboxlower

102 \newcommand*\setboxlower[2]{%
103   \settobox@vert\lower{#1}{#2}%
104 }

\setboxraise

105 \newcommand*\setboxraise[2]{%
106   \settobox@vert\raise{#1}{#2}%
107 }

\settobox@length The work for the \setbox... commands is done by \settobox@length. Inside
the length expression \width, \height, \depth, \totalheight are set to the
dimensions of the box.
#1: the property of the box that is to be changed (\wd, \ht, \dp)
#2: the box
#3: length expression
108 \def\settobox@length#1#2#3{%
109   \settobox@calc{#2}{#3}{#1#2=##1sp\relax}%
110 }

\settobox@horiz

111 \def\settobox@horiz#1#2#3{%
112   \settobox@calc{#2}{#3}{\setbox#2=\hbox{\kern#1##1sp\copy#2}}%
113 }

\settobox@vert

114 \def\settobox@vert#1#2#3{%
115   \settobox@calc{#2}{#3}{\setbox#2=\hbox{#1##1sp\copy#2}}%
116 }

\settobox@calc

117 \def\settobox@calc#1#2#3{%
118   \begingroup
119     \def\width{\wd#1}%
120     \def\height{\ht#1}%
121     \def\depth{\dp#1}%
122     \dimen@\ht#1\relax
123     \advance\dimen@\dp#1\relax
124     \def\totalheight{\dimen@}%
125     \setlength{\dimen@}{#2}%
126     \count@\dimen@
127     \def\x##1{\endgroup

```

```

128      #3%
129    }%
130    \expandafter\x\expandafter{\the\count@}%
131  }

132 </package>

```

3 Installation

3.1 Download

Package. This package is available on CTAN¹:

[CTAN:macros/latex/contrib/oberdiek/settobox.dtx](#) The source file.

[CTAN:macros/latex/contrib/oberdiek/settobox.pdf](#) Documentation.

Bundle. All the packages of the bundle ‘oberdiek’ are also available in a TDS compliant ZIP archive. There the packages are already unpacked and the documentation files are generated. The files and directories obey the TDS standard.

[CTAN:install/macros/latex/contrib/oberdiek.tds.zip](#)

TDS refers to the standard “A Directory Structure for T_EX Files” ([CTAN:tds/tds.pdf](#)). Directories with `texmf` in their name are usually organized this way.

3.2 Bundle installation

Unpacking. Unpack the `oberdiek.tds.zip` in the TDS tree (also known as `texmf` tree) of your choice. Example (linux):

```
unzip oberdiek.tds.zip -d ~/texmf
```

Script installation. Check the directory `TDS:scripts/oberdiek/` for scripts that need further installation steps. Package `attachfile2` comes with the Perl script `pdfatfi.pl` that should be installed in such a way that it can be called as `pdfatfi`. Example (linux):

```
chmod +x scripts/oberdiek/pdfatfi.pl
cp scripts/oberdiek/pdfatfi.pl /usr/local/bin/
```

3.3 Package installation

Unpacking. The `.dtx` file is a self-extracting `docstrip` archive. The files are extracted by running the `.dtx` through plain T_EX:

```
tex settobox.dtx
```

TDS. Now the different files must be moved into the different directories in your installation TDS tree (also known as `texmf` tree):

<code>settobox.sty</code>	→ <code>tex/latex/oberdiek/settobox.sty</code>
<code>settobox.pdf</code>	→ <code>doc/latex/oberdiek/settobox.pdf</code>
<code>settobox-example.tex</code>	→ <code>doc/latex/oberdiek/settobox-example.tex</code>
<code>settobox.dtx</code>	→ <code>source/latex/oberdiek/settobox.dtx</code>

If you have a `docstrip.cfg` that configures and enables `docstrip`’s TDS installing feature, then some files can already be in the right place, see the documentation of `docstrip`.

¹<http://ftp.ctan.org/tex-archive/>

3.4 Refresh file name databases

If your $\text{T}_{\text{E}}\text{X}$ distribution (te $\text{T}_{\text{E}}\text{X}$, mik $\text{T}_{\text{E}}\text{X}$, ...) relies on file name databases, you must refresh these. For example, te $\text{T}_{\text{E}}\text{X}$ users run `texhash` or `mktextlsr`.

3.5 Some details for the interested

Attached source. The PDF documentation on CTAN also includes the `.dtx` source file. It can be extracted by AcrobatReader 6 or higher. Another option is `pdftk`, e.g. unpack the file into the current directory:

```
pdftk settobox.pdf unpack_files output .
```

Unpacking with $\text{L}^{\text{A}}\text{T}_{\text{E}}\text{X}$. The `.dtx` chooses its action depending on the format:

plain $\text{T}_{\text{E}}\text{X}$: Run `docstrip` and extract the files.

$\text{L}^{\text{A}}\text{T}_{\text{E}}\text{X}$: Generate the documentation.

If you insist on using $\text{L}^{\text{A}}\text{T}_{\text{E}}\text{X}$ for `docstrip` (really, `docstrip` does not need $\text{L}^{\text{A}}\text{T}_{\text{E}}\text{X}$), then inform the autodetect routine about your intention:

```
latex \let\install=y\input{settobox.dtx}
```

Do not forget to quote the argument according to the demands of your shell.

Generating the documentation. You can use both the `.dtx` or the `.drv` to generate the documentation. The process can be configured by the configuration file `ltxdoc.cfg`. For instance, put this line into this file, if you want to have A4 as paper format:

```
\PassOptionsToClass{a4paper}{article}
```

An example follows how to generate the documentation with pdf $\text{L}^{\text{A}}\text{T}_{\text{E}}\text{X}$:

```
pdflatex settobox.dtx
makeindex -s gind.ist settobox.idx
pdflatex settobox.dtx
makeindex -s gind.ist settobox.idx
pdflatex settobox.dtx
```

4 Catalogue

The following XML file can be used as source for the [\$\text{T}_{\text{E}}\text{X}\$ Catalogue](#). The elements `caption` and `description` are imported from the original XML file from the Catalogue. The name of the XML file in the Catalogue is `settobox.xml`.

```
133 <?catalogue>
134 <?xml version='1.0' encoding='us-ascii'?>
135 <!DOCTYPE entry SYSTEM 'catalogue.dtd'>
136 <entry datestamp='$Date$' modifier='$Author$' id='settobox'>
137   <name>settobox</name>
138   <caption>Assigning dimensions of a box to a length register.</caption>
139   <authorref id='auth:oberdiek' />
140   <copyright owner='Heiko Oberdiek' year='2000,2006-2008' />
141   <license type='lppl1.3' />
142   <version number='1.4' />
143   <description>
144     Commands to assist the reuse of boxes (set up by <tt>\sbox</tt> or
145     by the <tt>\lrbox</tt> environment); the <tt>\settobox...</tt>
146     commands behave similarly to the <tt>\settowidth</tt> (etc.)
147     commands. For example:
148     <pre>
```

```

149     \newsavebox{\mybox}
150     \newlength{\mylength}
151     \sbox{\mybox}{Hello World}
152     \settoboxwidth{\mylength}{\mybox}
153 </pre>
154 <p/>
155     The package is part of the <xref refid='oberdiek'>oberdiek</xref> bundle.
156 </description>
157 <documentation details='Package documentation'
158     href='ctan:/macros/latex/contrib/oberdiek/settobox.pdf' />
159 <ctan file='true' path='/macros/latex/contrib/oberdiek/settobox.dtx' />
160 <miktex location='oberdiek' />
161 <texlive location='oberdiek' />
162 <install path='/macros/latex/contrib/oberdiek/oberdiek.tds.zip' />
163 </entry>
164 </catalogue>

```

5 History

[2000/02/11 v1.0]

- First public release, written as answer in the newsgroup [de.comp.text.tex](#): “Die Hoehe von Minipages und Bild”²

[2000/09/07 v1.1]

- Documentation added.
- CTAN release.

[2006/02/20 v1.2]

- \setboxwidth, \setboxheight, \setboxdepth added.
- Box move commands added.
- DTX framework.
- LPPL 1.3

[2007/04/11 v1.3]

- Line ends sanitized.

[2008/08/11 v1.4]

- Code is not changed.
- URLs updated.

6 Index

Numbers written in *italic* refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; plain numbers refer to the code lines where the entry is used.

	Symbols		\~	35
\@makeother	33		
\	37		

²Url: <http://groups.google.com/group/de.comp.text.tex/msg/c3f6446f54f66c02>

\backslash □	36	\backslash newsavebox	8, 149
		\backslash noindent	38
A		P	
\backslash active	35	\backslash pagestyle	13
\backslash addtolength	85	\backslash par	29, 40, 48
\backslash advance	123	\backslash parindent	11
		\backslash parskip	12
B		\backslash ProvidesPackage	78
\backslash begin	52		
C		R	
\backslash catcode	35, 36	\backslash raggedright	31
\backslash copy	112, 115	\backslash raise	106
\backslash count@	126, 130		
D		S	
\backslash depth	65, 70, 121	\backslash sbox	21, 44, 144, 151
\backslash detokenize	32	\backslash scantokens	39
\backslash dimen@	122, 123, 124, 125, 126	\backslash setbox	112, 115
\backslash do	33	\backslash setboxdepth	2, 57, 70, 93
\backslash documentclass	3	\backslash setboxheight	2, 55, 56, 69, 90, 93
\backslash dospecials	34	\backslash setboxlower	2, 64, 102
\backslash dp	82, 85, 94, 121, 123	\backslash setboxmoveleft	2, 58, 60, 96
		\backslash setboxmoveright	2, 63, 67, 99
E		\backslash setboxraise	65, 105
\backslash end	73	\backslash setboxright	2
F		\backslash setboxwidth	2, 54, 61, 68, 87
\backslash fbox	46	\backslash setlength	10, 11, 12, 80, 81, 82, 84, 125
\backslash fboxsep	10	\backslash settobox	145
		\backslash settobox@calc	109, 112, 115, 117
H		\backslash settobox@horiz	97, 100, 111
\backslash hbox	112, 115	\backslash settobox@length	88, 91, 94, 108
\backslash height	56, 57, 64, 69, 120	\backslash settobox@vert	103, 106, 114
\backslash ht	81, 84, 91, 120, 122	\backslash settoboxdepth	1, 82
		\backslash settoboxheight	1, 81
K		\backslash settoboxtotalheight	1, 83
\backslash kern	112	\backslash settoboxwidth	1, 80, 152
		\backslash settowidth	146
L		T	
\backslash lower	103	\backslash test	15, 28, 54, 55, 56, 57, 58, 59, 63, 64, 65, 66
M		\backslash texttt	39
\backslash makeatletter	27	\backslash the	130
\backslash makeatother	50	\backslash totalheight	124
\backslash mybox	8, 17, 21, 22, 44, 46, 54, 55, 56, 57, 58, 60, 61, 63, 64, 65, 67, 68, 69, 70, 149, 151, 152		
\backslash mylength	150, 152	U	
		\backslash usebox	46
N		\backslash usepackage	5, 6
\backslash NeedsTeXFormat	77		
\backslash newcommand	28, 80, 81, 82, 83, 87, 90, 93, 96, 99, 102, 105	W	
\backslash newlength	150	\backslash wd	80, 88, 119
		\backslash width	54, 61, 63, 68, 119
		X	
		\backslash x	32, 39, 127, 130